

U-20 RS-PCM  
KEYBOARD

U-220 RS-PCM  
SOUND MODULE



SN-U110-12  
SAX & TROMBONE

SAMPLE COLLECTION BY *nic*

# INFORMATION

© 2017 by *nion*, all rights reserved. If needed, contact me through [info@nion.eu](mailto:info@nion.eu).

All samples have been recorded at 48,000 kHz/24-bit. In some instruments, some noise may be heard at the end of samples, due to the analogue recording and the base material from the U-20/220. This could not be avoided because the U-20/220 does not have a digital output. Noise reduction has not been applied, as it also alters the sound.

All usable notes have been sampled, from midi number 024 to 127. Most instruments stop before number 127 in the U-20/220, these (empty) samples have, of course, not been included. Notes below 024 have been recreated by lowering the sample, at this depth the difference is marginal, and lower samples would be very large. If included, the total size of the library would increase a lot.

Sustained tones have been sampled up to the point where they loop (and then, looped).

V-switch tones have been compiled using their original sample sets if available (e.g., Saxophone Switch 1, compiled from Saxophone p 2 and Saxophone mf 1). In Kontakt, the switch point can be edited in the mapping editor. Or even changed into a v-mix tone, if you like, using the Kontakt auto X-fade tool.

Factory tones have the prefix number F---. Newly created tones (e.g., not available on the original expansion card) have the prefix U---.

On the front panel of the Kontakt patch, you can control the amount of reverb, chorus, delay and flanger, effects that are also available in the U-220 hardware.

Of course, there are unlimited possibilities in Kontakt to create new sounds!

# TONE LIST

SN-U110-12

SAX & TROMBONE

No.	Tone Name	Type	Remarks
FACTORY TONES			
SAXOPHONE			
F001	Saxophone Switch 1	V-switch	Mezzo forte / piano (v=100). Looped. Compiled using Saxophone P 2 and MF 1.
F002	Saxophone Switch 2	V-switch	Bright. Mezzo forte / piano (v=100). Looped. Compiled using Saxophone P 3 and MF 2.
F003	Saxophone Switch 3	V-switch	Forte / mezzo forte (v=100). Looped. Compiled using Saxophone MF 1 and FF 1.
F004	Saxophone Switch 4	V-switch	Bright. Forte / mezzo forte (v=100). Looped. Compiled using Saxophone MF 2, FF 1 and SW 4.
F005	Saxophone p 1	Single	Mellow. Piano. Looped.
F006	Saxophone p 2	Single	Piano. Looped. Compiled using Saxophone P1 and P2.
F007	Saxophone p 3	Single	Bright. Piano. Looped. Compiled using Saxophone P1, P2 and P3.
F008	Saxophone mf 1	Single	Mezzo forte. Looped.
F009	Saxophone mf 2	Single	Bright, Mezzo forte. Looped. Compiled using Saxophone MF 1 and MF 2.
F010	Saxophone ff 1	Single	Fortissimo. Looped.
TROMBONE			
F011	Trombone Switch 1	V-switch	Mezzo forte / piano (v=100). Looped. Compiled using Trombone P and MF.
F012	Trombone Switch 2	V-switch	Fortissimo / mezzo forte (v=100). Looped. Compiled using Trombone MF and FF.
F013	Trombone p	Single	Piano. Looped.
F014	Trombone mf	Single	Mezzo forte. Looped.
F015	Trombone ff	Single	Fortissimo. Looped.

# TONE LIST

SN-U110-12		SAX & TROMBONE	
No.	Tone Name	Type	Remarks
TRUMPET/TROMBONE			
F016	Trumpet/Trombone Switch 1	V-switch	Mezzo forte / piano (v=100). Trombone, Trumpet (A#1). Looped. Compiled using Trombone P, MF, Trumpet/Trombone P and MF.
F017	Trumpet/Trombone Switch 2	V-switch	Fortissimo / mezzo forte (v=100). Trombone, Trumpet (A#1). Looped. Compiled using Trombone MF, FF, Trumpet/Trombone MF and FF.
F018	Trumpet/Trombone p	Single	Piano. Trombone, Trumpet (A#1). Looped. Compiled using Trombone P and Trumpet/Trombone P.
F019	Trumpet/Trombone mf	Single	Mezzo forte. Trombone, Trumpet (A#1). Looped. Compiled using Trombone MF and Trumpet/Trombone MF.
F020	Trumpet/Trombone ff	Single	Fortissimo. Trombone, Trumpet (A#1). Looped. Compiled using Trombone FF and Trumpet/Trombone FF.
USER TONES			
SAXOPHONE			
U001	Saxophone ff 2	Single	Bright. Fortissimo. Looped. Compiled using the fortissimo samples from Saxophone SW 4 and FF 1.
TROMBONE			
U002	Trombone Switch 3	V-switch	Piano / mezzo forte / forte (v=65/97). Looped. Compiled using Trombone P, MF and FF.
TRUMPET/TROMBONE			
U003	Trumpet/Trombone Switch 3	V-switch	Piano / mezzo forte/forte (v=65/97). Trombone, Trumpet (A#1). Looped. Compiled using Trumpet/Trombone P, MF and FF.
TRUMPET			
U004	Trumpet Switch 1	V-switch	Mezzo forte / piano (v=100). Looped. Compiled using Trumpet/Trombone P and MF.
U005	Trumpet Switch 2	V-switch	Fortissimo / mezzo forte (v=100). Looped. Compiled using Trumpet/Trombone MF and FF. Trumpet starts at 046.
U006	Trumpet Switch 3	V-switch	Piano / mezzo forte/forte (v=65/97). Looped. Compiled using Trumpet/Trombone P, MF and FF.
U007	Trumpet p	Single	Piano. Looped. Compiled using Trumpet/Trombone P.
U008	Trumpet mf	Single	Mezzo forte. Looped. Compiled using Trumpet/Trombone MF.
U009	Trumpet ff	Single	Fortissimo. Looped. Compiled using Trumpet/Trombone FF.